

# GM Voices

These may be played polyphonically on any MIDI channel except 10, which is reserved for drums. The program (patch) number for each is shown.

## ***Piano:***

- 1 Acoustic piano
- 2 Bright piano
- 3 Grand piano
- 4 Honky-tonk piano
- 5 Rhodes piano 1
- 6 Chorused piano 2
- 7 Harpsichord
- 8 Clavinet

## ***Chromatic Percussion:***

- 9 Celesta
- 10 Glockenspiel
- 11 Music box
- 12 Vibraphone
- 13 Marimba
- 14 Xylophone
- 15 Tubular bell
- 16 Dulcimer

## ***Organ:***

- 17 Hammond organ
- 18 Percussive organ
- 19 Rock organ
- 20 Church organ
- 21 Reed organ
- 22 Accordion
- 23 Harmonica
- 24 Tango accordion

## ***Guitar:***

- 25 Acoustic nylon guitar
- 26 Acoustic steel guitar
- 27 Jazz guitar
- 28 Clean guitar
- 29 Muted guitar
- 30 Overdriven guitar
- 31 Distortion guitar
- 32 Guitar harmonics

## ***Bass:***

- 33 Acoustic bass
- 34 Finger bass
- 35 Picked bass
- 36 Fretless bass
- 37 Slap bass 1
- 38 Slap bass 2
- 39 Synth bass 1
- 40 Synth bass 2

## ***Strings:***

- 41 Violin
- 42 Viola
- 43 Cello
- 44 Double bass
- 45 Tremolo strings
- 46 Pizzicato strings
- 47 Orchestral harp
- 48 Timpani

## ***Ensemble:***

- 49 Strings 1
- 50 Strings 2
- 51 Synth strings 1
- 52 Synth strings 2
- 53 Voice aahs
- 54 Voice oohs
- 55 Synth voice
- 56 Orchestra hit

## ***Brass:***

- 57 Trumpet
- 58 Trombone
- 59 Tuba
- 60 Muted trumpet
- 61 French horn
- 62 Brass
- 63 Synth brass 1
- 64 Synth brass 2

**Reed:**

65 Soprano sax  
66 Alto sax  
67 Tenor sax  
68 Baritone sax  
69 Oboe  
70 English horn  
71 Bassoon  
72 Clarinet

**Pipe:**

73 Piccolo  
74 Flute  
75 Recorder  
76 Pan flute  
77 Bottle blow  
78 Shakuhachi  
79 Whistle  
80 Ocarina

**Synth Lead:**

81 Square wave  
82 Sawtooth  
83 Calliope  
84 Chiff lead  
85 Charang  
86 Solo synth lead  
87 Bright saw  
88 Bass and lead

**Synth Pad:**

89 Fantasia  
90 Warm pad  
91 Poly synth  
92 Space pad  
93 Bowed glass  
94 Metal  
95 Halo pad  
96 Sweep pad

**Synth Effects:**

97 Ice rain  
98 Soundtrack  
99 Crystal  
100 Atmosphere  
101 Brightness  
102 Goblin  
103 Echo drops  
104 Star theme

**Ethnic:**

105 Sitar  
106 Banjo  
107 Shamisen  
108 Koto  
109 Kalimba  
110 Bagpipe  
111 Fiddle  
112 Shanai

**Percussive:**

113 Tinkle bell  
114 Agogô  
115 Steel drums  
116 Woodblock  
117 Taiko drum  
118 Melodic tom  
119 Synth drum  
120 Reverse cymbal

**Sound effects:**

121 Guitar fret  
122 Breath  
123 Seashore  
124 Bird tweet  
125 Telephone Ring  
126 Helicopter  
127 Applause  
128 Gunshot

# GM Drums

These are played only on channel 10, one drum per note. The MIDI note number for each is shown.

|                   |                    |
|-------------------|--------------------|
| 35 Bass Drum 2    | 59 Ride Cymbal 2   |
| 36 Bass Drum 1    | 60 High Bongo      |
| 37 Side Stick     | 61 Low Bongo       |
| 38 Snare Drum 1   | 62 Mute High Conga |
| 39 Hand Clap      | 63 Open High Conga |
| 40 Snare Drum 2   | 64 Low Conga       |
| 41 Low Tom 2      | 65 High Timbale    |
| 42 Closed Hi-hat  | 66 Low Timbale     |
| 43 Low Tom 1      | 67 High Agogo      |
| 44 Pedal Hi-hat   | 68 Low Agogo       |
| 45 Mid Tom 2      | 69 Cabasa          |
| 46 Open Hi-hat    | 70 Maracas         |
| 47 Mid Tom 1      | 71 Short Whistle   |
| 48 High Tom 2     | 72 Long Whistle    |
| 49 Crash Cymbal 1 | 73 Short Guiro     |
| 50 High Tom 1     | 74 Long Guiro      |
| 51 Ride Cymbal 1  | 75 Claves          |
| 52 Chinese Cymbal | 76 High Wood Block |
| 53 Ride Bell      | 77 Low Wood Block  |
| 54 Tambourine     | 78 Mute Cuica      |
| 55 Splash Cymbal  | 79 Open Cuica      |
| 56 Cowbell        | 80 Mute Triangle   |
| 57 Crash Cymbal 2 | 81 Open Triangle   |
| 58 Vibra Slap     |                    |